Bill Redirect
Send data directly in a field of another software

Documentation: 05/11/2008

Use this documentation with the product : Bill Redirect 5.0J and more

Software configuration and integration service
It's free, fast, and efficient !
**Submit your case to info@billproduction.com
and receive a customized answer !**

Our Internet site: http://www.billproduction.com/

Email: info@BillProduction.com

This documentation demonstrate
How you can redirect the serial port data directly in a field of another software

Step #1
Download and install Bill Redirect software **http://www.billproduction.com/Bill_COMtoKB.ZIP**

Step #2
 Disable all except the Serial Port section. **Set the Switch to OFF**

Step #3

Bill Redirect Serial/File/TCP Port and Keyboard V5.0J (Trial Version)

Password ******

Order now ...

Programmer: Steve
Request: info@billproduction.com
About me: www.BillProduction.com

Bill Production Softwares

Minimze to Tray Icon

Type in the password field: FFINDER

To open this FIELD FINDER window:

Bill Redirect FIELD FINDER

Step 1: Start your software.

Step 2: In your software, go where is the field.

Application title:

Fields found:

Step 3: To find the field's number Click this button:

FIELDS INDENTIFICATION

Step 4: In the list box, double click on the desired Field.

Step #4

Click on your: Start Menu

Step #5

Bill Redirect FIELD FINDER

Step 1: Start your software.

Step 2: In your software, go where is the field.

Application title:

<65654>

Fields found:

304
303
1502
40965

Step 3: To find the field's number Click this button:

FIELDS INDENTIFICATION

Step 4: In the list box, double click on the desired Field.

At this moment you can see the Taskbar fields.

Click on button: FIELDS INDENTIFICATION to find the field Start

The Field number 304 appear on your 304 Start Button.

* Depending on your windows version, this number can change.

The Taskbar title is: <65654>

* Depending on your windows version, this number can change.

Step #6

Click on button: Configuration.
Enter the Serial Port Number where your peripheral is connected.
Chose the good: Bauds, Parity and DataBits

Click on button: Configuration

Click on button: Add

Enter in this field: {SERIAL_RX}

Enter in this field: {TX_FIELD[<65654>,304,RX_DATA]}
<65654> is the window title and 304 the field number, found in Step #5

X ASCII
to remove

+ADD
REMOVE

Click on button: Add

ASCII to Remove

Computers use ASCII code to represent letters and numbers. For instance the capital letter A is represented by 65. The capital letter B is 66 ... Enter the ASCII number to REMOVE (0 to 255):

OK

Annuler

13

Enter in this field: 13

X ASCII
to remove

13

+ADD
REMOVE

Click on button: Add

ASCII to Remove

Computers use ASCII code to represent letters and numbers. For instance the capital letter A is represented by 65. The capital letter B is 66 ... Enter the ASCII number to REMOVE (0 to 255):

OK

Annuler

10

Enter in this field: 10

Step #8

OK

Click on button: OK

Save Configuration

Click on button: Save Configuration

At this Step:
- All data received by your Serial Port appear on your Start Button.

Do the same steps to redirect the Serial Data to your application !