

Bill Redirect Send data directly in your Microsoft Access

Documentation: 18/11/2008



Use this documentation with the product : Bill Redirect 5.0J and more

Software configuration and integration service It's free, fast, and efficient ! Submit your case to info@billproduction.com and receive a customized answer !

Our Internet site: <u>http://www.billproduction.com/</u>

Email: info@BillProduction.com

This documentation demonstrate how Bill Redirect can sent Serial Scanner (Barcode, Proximity, scale...) Reader numbers directly in Microsoft Access



Microsoft[®]



Download and install Bill Redirect software http://www.billproduction.com/Bill_COMtoKB.ZIP







Step #5

Microsoft Access Configuration

You can download this example via this link:

(MS Access 2003 and more)

http://www.billproduction.com/MSAccess01.zip

The following demonstrates how you can receive Bill Redirect data in Microsoft Access via a timer.

- 1. Create a sample database Sample.mdb
- 2. Create a table with 3 fields:

Field Name	Data Type	
ID_Barcode	Text	
ID_Date	Date/Time	
ID_Time	Date/Time	

Save this Table to: **BillRedirect** * *Important: Use no Primary Key* !

- 3. Create a new form and open it in "Design view"
- 4. Add on this form 3 Text Box:

Form example		Each Text Box Properties	
		Name	Data / Control Source
Barcode:	ID_Barcode	TextBoxBarcode	ID_Barcode
Date:	ID_Date	 TextBoxDate	ID_Date
Time:	ID_Time	 TextBoxTime	ID_Time

5. Set Form properties Data / Source: BillRedirect

6. Insert the following source code:

```
Private Sub Form Load()
      Me.TimerInterval = 100
  End Sub
  Public Sub Form_Timer()
      Call RX_BillRedirect
  End Sub
  Public Sub RX_BillRedirect()
      On Error GoTo BillRedEnd
      Const TheDirectory = "c:\BillProduction.cfg\"
      Dim TheFile As String
      Dim TheData As String
      TheFile = Dir(TheDirectory & "*.OUT")
      If TheFile <> "" Then
          Open TheDirectory & TheFile For Input As #1
              Line Input #1, TheData
              'The data is in the variable: TheData
              '...HERE... ADD COMMANDS TO APPEND DATA TO YOUR TABLE
              '----[Example]-----
              DoCmd.GoToRecord , , acNewRec
              TextBoxBarcode.SetFocus
              TextBoxBarcode.Text = TheData
              TextBoxDate.SetFocus
              TextBoxDate.Text = Date
              TextBoxTime.SetFocus
              TextBoxTime.Text = Time
              '----[Example]------
          Close #1
          Kill TheDirectory & TheFile
      End If
      Exit Sub
  BillRedEnd:
      Debug.Print Err.Description
      Close #1
  End Sub
7. Close and save the form
8. Open the form in mode "Form View"
```

At this step if your configuration is correct you can see the data received by your serial peripheral appear in Microsoft Access

For more information, consult the product manual: <u>http://www.billproduction.com/Bill_Redirect_Manual.pdf</u>

Software configuration and integration service

It's free, fast, and efficient ! Submit your case to <u>info@billproduction.com</u> and receive a customized answer !